
Configure Texmaker
Commands
Quick Build
Editor
Shortcuts
Commands (% : filename without extension - @ : line number)
LaTeX
latex -interaction=nonstopmode %.tex
PdfLaTeX
pdflatex -synctex=1 -interaction=nonstopmode %.tex
Use a "build" subdirectory for output files
XeLaTeX
xelatex -synctex=1 -interaction=nonstopmode %.tex
Latexmk
Bib(la)tex
bibtex %
Makeindex
makeindex %.idx
dvips
dvips -o %.ps %.dvi
Dvipdfm
dvipdfm %.dvi
ps2pdf
ps2pdf %.ps
metapost
mpost --interaction nonstopmode
Asymptote
"C:/Program Files/Asymptote/asy.exe" %.asy
ghostscript
"C:/Program Files/gs/gs9.05/bin/gswin32c.exe"
R Sweave
Add to PATH
Dvi Viewer
"C:/Program Files/MiKTeX 2.9/miktex/bin/yap.exe" %.dvi
PS Viewer
"C:/Program Files/Ghostgum/gsview/gsview32.exe" %.ps
Pdf Viewer
Built-in Viewer
Embed
External Viewer
rogram Files/Adobe/Reader 10.0/Reader/AcroRd32.exe" %.pdf
OK
Cancel


Configure Texmaker
Commands
Quick Build
Editor
Shortcuts
Quick Build Command
LaTeX + dvips + View PS
LaTeX + View DVI
PdfLaTeX + View PDF
LaTeX + dvipdfm + View PDF
LaTeX + dvips + ps2pdf + View PDF
LaTeX + Asymptote + LaTeX + dvips + View PS
PdfLaTeX + Asymptote + PdfLaTeX + View Pdf
LatexMk + View PDF
XeLaTeX + View PDF
User : (% : filename without extension)
-interaction=nonstopmode %.tex|bibtex %.aux|latex -interaction=nonstopmode %.tex|latex -interaction=nonstopmode %.tex|xdvi %.dvi
wizard
(the commands must be separated by '|')
Don't launch a new instance of the viewer if the dvi/ps/pdf file is already opened
OK
Cancel